



Production Planning End User Manual



Process order Execution

last modified on May 06, 2021





Table of Contents

1.	Process order Execution –
1 1	Process order Execution





Objective

This document will explain Process order Execution in Production Planning (PP) for Overburden(OB) Shovel Dumper Departmental Process.

Prerequisites

Authorizations must be available in SAP.

PP Master Data.






Process

STEP 1- Create Monthly Process Order

T-Code - COR1 - Create Process order




- > Enter your <u>Material Number</u>
- > Enter your Plant No
- > Enter your <u>Process Order Type</u> then Press Enter.






- > Enter the Quantity of the material
- > Enter Start Date(Current Date should be mention).
- ➤ Enter End Date(Month End Date) then Press Enter.




> Select Your Production Version Then Press Choose button as mention below.








> After That Press Save Button.



Note the Unique <u>Process order Number</u> that will be generated as mention below after saving.








STEP 2- Release of Monthly Process Order

T-Code – COR2 – Change Process order



- Enter the <u>Process order number</u> then Press Enter.
- > After that click on the Release button then Save it .



▶ Process order will be saved Process order 70003022 saved and message will be shown.






<u>STEP 3 - Transfer of control recipe</u> data to PI sheet using control recipe monitor

T-Code – CO53 – Control Receipt monitor

- > Enter your Plant No
- > Enter your Process Order Number
- > Then click on Display button Display



Click on Select all button as per mention below.







> Then click on the send button.



After clicking the refresh button , status will be change from created to sent.








STEP 4 - Shift Wise PI sheet entry.


T-Code – CO60 – Find PI sheet

- Maintain Plant and Process Order Number.
- > Then Click on Execute Button






Select the 2nd PI sheet for filling drilling information and click on the edit PI sheet button as mention as shown below.







> Fill the correct Information in PI sheet.




> Send the data to database.








Comeback and select the 1st sheet. For blasting Information.



> Fill the Required Blasting detail and save it.








STEP 5 - Production confirmation shift wise.


➤ Navigate to 3rd PI Sheet for Production Confirmation.



Maintain Production <u>Date</u>, <u>Shift & Select Operation</u> on <u>recall</u> and click on the <u>REFRESH/RECALL button</u>.




Scroll down and select the simulation mode on <u>S</u> and click on button to simulate.





 \triangleright Similarly, select the simulation mode on \underline{X} and click on $\underline{\parallel}$ SIMULATE/CONFIRM PObutton for conformation.








STEP 6 - Shift Note generation.


Fill the message you want to send on Message text and click on button to generate shift note.



- > Shift note will be generated as per shown above on shift note number.
- > TO display generated shift note.

T-code-SHN3-Display Shift note


> Enter the generated shift note number then press enter.








> Click on the Print notification as per path below.



Insert the Output Device and click on Print Preview button.



Again Mention output Device and click on print preview.







> Shift Note Preview.

<u>Shift-Wise Production Report (Opencast, Over Burden) Departmental</u> <u>Form 1-B</u>

Name Of The Subsidiary:

Name Of The Area:

Name Of The Mine: Name Of The Pitt:

QUARRY 1/OB BENCH1,BENCH1

Name Of The Seam: Production Date:

SEAM 1 May 5, 2021

Shift: SF1A

(a	J	x	ca	va	tor	

SLNO	NAME/NO	BENCH NO	Н	ours	O		
			Working	BD Idle	Solid	Re-Handled	Total
10	EXC2803	BENCH1	2:00	06:00		8	0
13	8	TOTAL	8 9			6	0

1(b). Surface Miner

2. Drag Line

3(a). Dumper/Tipper - Departmenta

SLNO	NAME/NO	BENCH NO	Hours		DUMPER FACTOR	TRIPS NO	OB Quantity(CUM)			
			Working	BD	Idle			Solid	Re-Handled	Total
1	D11143	BENCH1	2:00	0	06:00	15	00006	90	0 80	90
	0	TOTAL	3	07	2 9	0	00006		0 8	90

3(b). Dumper/Tipper - Hired

4. Drill






STEP 7- Perform manual goods issue (GI).(For Component Materials)

T-Code - MIGO

> Enter your Process Order and press Enter.



Maintain the <u>quantity</u>, <u>Storage location</u>, <u>Batch Number(if any)</u>, & Select <u>on OK</u> material.








Now Click on the <u>Check</u> button to see if document is ok or not.



Click on the Post button to Post the Document.








STEP 9 - Check Stock posting

T-Code - MMBE

- ➤ Here you can see the of the material stock quantity.
- Maintain relevant information like material you want to see and plant in which you have stored. and click on execute button.



Here you can see the stock quantity of material as shown below.

